

Guide to IPv6 - Troubleshoot IPv6 Problems

Guide to IPv6

[Get Started With IPv6](#)

[IPv6 Server Administration](#)

[Troubleshoot IPv6 Problems](#)

Overview

This documentation lists common IPv6 problems, and steps to resolve them.

Confirm that IPv6 functions on the server

To confirm whether IPv6 functions on your server, use the `ping6` command to ping another server, and to ping the IPv6 server.

Note:

If the `ping6` command fails, we recommend that you use the `traceroute` command to begin your investigation. This command displays detailed information about the path that information travels between one server and another, and lists the associated routers.

Ping another server from the IPv6 server

To confirm that your server can reach other servers via IPv6, run the following command as the `root` user on your IPv6 server:

```
ping6 ipv6.google.com
```

If IPv6 functions on your server, this command's output resembles the following example:

```
PING ipv6.google.com(2001:4860:b002::68) 56 data bytes
64 bytes from 2001:4860:b002::68: icmp_seq=0 ttl=59 time=58.4 ms
64 bytes from 2001:4860:b002::68: icmp_seq=1 ttl=59 time=56.4 ms
64 bytes from 2001:4860:b002::68: icmp_seq=2 ttl=59 time=62.1 ms
```

Important:

If the command's output does **not** resemble this example, IPv6 does **not** function on your server. You **must** resolve this issue before you can use cPanel & WHM with IPv6.

Ping the IPv6 server from another server

To confirm that other servers can reach your server via IPv6, run the following command as the `root` user on another server:

```
ping6 2001:db8:10fe::5000
```

Note:

In this example, replace `2001:db8:10fe::5000` with your server's IPv6 address.

If IPv6 functions on your server, this command's output resembles the following example:

```
PING 2001:0db8:85a3::8a2e:0370:7334 56 data bytes
64 bytes from 2001:db8:10fe::5000: icmp_seq=1 ttl=62 time=0.847 ms
64 bytes from 2001:db8:10fe::5000: icmp_seq=2 ttl=62 time=0.994 ms
64 bytes from 2001:db8:10fe::5000: icmp_seq=3 ttl=62 time=0.909 ms
```

Important:

If the command's output does **not** resemble this example, IPv6 does **not** function on your server. You **must** resolve this issue before you can use cPanel & WHM with IPv6.

Netmask misconfiguration

IPv6 uses the same netmask as IPv4, but expresses it in CIDR notation. Typically, interfaces display this netmask and the IPv6 address together.

Make **certain** that you enter the correct netmask for your network when you add IPv6 addresses to your server. For example, IPv6 networks can use a /128 CIDR mask to route single addresses and ranges, but recommended rollout procedures typically use the /64 netmask instead. If you enter an incorrect netmask for your network, your server may not function correctly.

Neighbor Delivery Protocol problems

IPv6 replaces IPv4's Address Resolution Protocol (ARP) and Internet Control Message Protocol (ICMP) with the [Neighbor Discovery Protocol \(NDP\)](#). NDP uses multicast to solicit responses from the router and other network devices. Some configurations of hardware, VLANs, and software bridges can interfere with NDP and may cause network issues. For example, KVM-based virtualization uses the Linux software bridge, which filters superfluous traffic and may therefore interfere with NDP.

To resolve these issues, upgrade to a newer Linux kernel. If the problems persist, you may need to make additional changes to your configuration for IPv6 to function correctly.

For steps to resolve this issue on a KVM server, read the following posts:

- [CentOS-virt mailing list's Issues with routing IPv6 to KVM Guests thread](#)
- [Patchwork's Patchwork bridge is not forwarding ICMP6 neighbor solicitation to KVM guest post](#)
- [Launchpad's Multicast snooping on bridge breaks ICMP6 neighbor solicitation for KVM guests post](#)

Check the IPv6 addresses on your server

In some cases, you may need to check the assigned IPv6 addresses on your server. To do this, use the following command:

```
ip -6 addr show
```

This command displays all of the server's IPv6 addresses, network devices, and their configurations.

Note:

This command's output includes local link and non-global addresses. To display global addresses, run the following command:

```
ip -6 addr show scope global
```

Additional documentation

Suggested documentation [For cPanel users](#) [For WHM users](#) [For developers](#)

- [Guide to IPv6](#)
- [IPv6 Ranges](#)
- [Guide to IPv6 - How to Get Started With IPv6](#)
- [Guide to IPv6 - IPv6 Server Administration](#)
- [Guide to IPv6 - Troubleshoot IPv6 Problems](#)

Content by label

There is no content with the specified labels



- [Guide to IPv6](#)
- [IPv6 Ranges](#)
- [How to Configure Reverse DNS for BIND in WHM](#)
- [Guide to IPv6 - How to Get Started With IPv6](#)
- [Guide to IPv6 - IPv6 Server Administration](#)

- [WHM API 1 Functions - ipv6_range_usage](#)
- [WHM API 1 Functions - ipv6_disable_account](#)
- [WHM API 1 Functions - ipv6_range_add](#)
- [WHM API 1 Functions - ipv6_enable_account](#)
- [WHM API 1 Functions - ipv6_range_remove](#)