

How to Edit FTP Server Configuration from the Command Line

Overview
Determine your FTP server
ProFTP Configuration
Additional documentation

Overview

This document explains how to manually edit the FTP server's configuration from the command line.

Determine your FTP server

To determine which FTP server your server uses, log in to your server via SSH as the `root` user and run the `grep ftpserver /var/cpanel/cpanel.config` command.

You will receive one of the following two results:

```
ftpserver=proftpd  
ftpserver=pure-ftpd
```

Follow the instructions below that correspond to your FTP server type.

Pure-FTP configuration

To edit the FTP configuration for Pure-FTP, perform the following steps:

1. Use your preferred text editor to create or edit the `/var/cpanel/conf/pureftpd/local` file.
2. Enter your changes in the `local` file.

Note:

For example, to set the `ForcePassiveIP` setting to the IP address, enter the following in the `local` file:

```
ForcePassiveIP: 203.0.113.0
```

To clear that value, change the `local` file to use the following setting:

```
ForcePassiveIP: ~
```

3. To apply your changes, perform a force update of FTP with the `/scripts/setupftpservice pure-ftpd --force` command.

ProFTP Configuration

To edit the FTP configuration for ProFTP, perform the following steps:

1. Use your preferred text editor to create or edit the `/var/cpanel/conf/proftpd/local` file.
2. Enter your changes in the `local` file.
3. To apply your changes, perform a force update of FTP with the `/scripts/setupftpservice proftpd --force` command.

Additional documentation

Suggested documentation For cPanel users For WHM users For developers

- [How to Edit FTP Server Configuration from the Command Line](#)
- [How to Clear a Full Partition](#)
- [AutoFixer](#)
- [How to Resolve Password Authentication Failed Errors in PostgreSQL](#)
- [The scl Utility](#)

- [AutoConfig and Autodiscover](#)
- [Connect to Web Disk with Third-Party Software](#)
- [From WHM to Website](#)
- [Guide to Git - Deployment](#)
- [Service Subdomains Explanation](#)

- [How to Enable FTP Passive Mode](#)
- [LiteSpeed Web Server](#)
- [FTP](#)
- [How to Configure Your SFTP Client](#)
- [How to Restore Missing FTP Interfaces in cPanel](#)

- [cPanel API 2 Modules - FTP](#)
- [UAPI Modules - Ftp](#)
- [cPanel API 2 Functions - Ftp::addftp](#)
- [cPanel API 1 Functions - Ftp::delftp](#)
- [cPanel API 1 Functions - Ftp::addftp](#)