

Initial Setup Wizard - Set Up IP Addresses


For cPanel & WHM version 62

[<< Step 2: Setup Networking](#)

[Step 4: Nameservers >>](#)

Initial Setup

Step 3 out of 6



Step 1:

[Agreement](#)

Step 2:

[Setup Networking](#)

Step 3:

Set Up IP Addresses

Step 4:

[Nameservers](#)

Step 5:

[Services](#)

Step 6:

[Set Up Quotas](#)

Set Up IP Addresses

This section allows you to add IP addresses to your server.



Important:

Your server **must** have at least one IP address, which will function as the primary IP address of your server. If you do not have an IP address, visitors **cannot** access your server.



Note:

If you do not wish to enter additional IP addresses, click *Skip This Step and Use Default Settings* to proceed to [Step 4: Nameservers](#).

Add New IP Address(es)

To add IP addresses, perform the following steps:

1. In the *IP Address(es) to Add* text box, enter your server's IP addresses.

**Note:**

Use CIDR notation to add multiple IP addresses simultaneously. For more information, refer to the *Quick CIDR Reference Table* to the right of the interface.

2. In the *Subnet Mask* text box, enter the appropriate subnet mask for your range of IP addresses.

**Note:**

This value defaults to 255 . 255 . 255 . 0.

3. Check to ensure that the displayed *Network/Ethernet Device* is correct (for example, *eth0*).
4. Click *Add IP(s)* to continue to [Step 4: Nameservers](#).

Current IP Addresses

The *Current IP Addresses* table displays the following information and options for your server's currently configured IP addresses.

Column	Description
<i>Interface</i>	The network device for that IP address (for example, <i>eth0</i>).
<i>IP</i>	The IP address. <div data-bbox="272 856 311 894" data-label="Image"></div> <div data-bbox="321 856 383 884" data-label="Section-Header">Note:</div> <div data-bbox="321 898 1279 926" data-label="Text"> <p>If your server uses 1:1 NAT, the interface displays <i>Local IP</i> and <i>Public IP</i> columns in place of the <i>IP</i> column.</p> </div>
<i>Notes</i>	This column indicates, for example, whether the IP address is a shared IP address, or whether the IP address is reserved.
<i>Actions</i>	If the server is not currently in use, the <i>Remove</i> option displays. Click <i>Remove</i> to remove the IP address from your server.

<< [Step 2: Setup Networking](#)

[Step 4: Nameservers](#) >>

Additional documentation

Content by label

There is no content with the specified labels

